ITS Product Guides



INFO TECHNOLOGY SUPPLY LTD.

Microsoft Windows Installation Procedure for DocSlide



Contents

Contents	2
Requirements	3
Operating System	
Components	3
Firewall and Network	3
Certificate	3
Installation Procedure	4
Installation of the Microsoft Net Core and CP Redist 2019 Component	4
Installation of the DocSlide Application	4
Admin Account Setup	6
Web Server Configuration	6
Authentication Type	7
Eula confirmation	7
Here you need to read DocSlide Eula and confirm that you agree with it	7
License activation	7
Language Selection	8
Restart DocSlide Service	8
Logging On to the DocSlide Admin Portal	9
Backup and Recovery	10

Requirements

Operating System

- Windows 10, Windows Server 2012 or newer
- 40 GB of free hard disc space
- 4 GB of RAM

Components

- You will need to download and install the latest Microsoft Net Core 8 component and CP Redist 2019
- A Links to the packages is provided below:

https://dotnet.microsoft.com/en-us/download/dotnet/thank-you/runtime-aspnetcore-8.0.15windows-hosting-bundle-installer

https://learn.microsoft.com/en-us/cpp/windows/latest-supported-vc-redist?view=msvc-160

Firewall and Network

• You need to open your firewall and network port 12120.

Certificate

• If you want to run the DocSlide portal using HTTPS, the administrator needs to create a certificate for the server's DNS name and upload it for further use.

Installation Procedure Installation of the Microsoft Net Core and CP Redist 2019 Component

Run the installation binary as administrator and follow the installer's instructions.

Installation of the DocSlide Application

1. Unzip the installation package.



2. Copy the DocSlide folder to the local hard drive

📥 + T	'his PC → Local Disk (C:) →		
	Name	Date modified	Туре
	🎉 Archive	29/11/2019 23:51	File folder
	퉬 backup	29/07/2020 11:57	File folder
es	퉬 DocSlide	29/07/2020 11:57	File folder
	퉬 homefolder	29/11/2019 23:55	File folder
	- inetrub	20/11/2010 22-12	File folder

3. In the DocSlide folder you will find install.cmd, run this as administrator.





4. Start the DocSlide Scanning Service

ile Action View	Help						
• • 🖻 🗟 i	9 🕞 🖬 🖽 🕨 🖬 🖬 🖬						
Services (Local)	Services (Local)						
	DCOM Server Process Launcher Description: The DCOM and DCOM numers in response COM and DCOM numers in response construction and the service launches revision site appendix of scalability revision site appendix of scalability revision site appendix of scalability revision statements and the service numerical of function property. It is strongly recommended that you have the DCOMLAUNCH service numing.	Norme C. DOLL Serve Docent Lance C. Dollar Association Service C. Dollar Manager C. Dollar Service C. Dollar Service C. Dagnostic Service Host C. Dag	Description The DCOM. Enables pair Enables the Registers an The Diagno The Diagno The Diagno The Diagno The Diagno The Diagno Coordinates it	Status Forming Forming Forming Forming Forming	Startup Type Automotic Manual (Trig., Manual (Trig., Automatic (D., Manual Automatic (D., Manual Automatic Automatic Automatic Automatic	Log De As Und Syste. Local Syste. Local Syste. Local Syste. Local Service Local Service Local Syste. Local Syste. Local Syste. Local Syste. Local Syste. Local Syste. Local Syste.	
		C. DNS Client	The DNS Cit.	Durning	Automatic (T.,	Network Service	
		La Docsede scenning service	Toronto and		Automatic	Local Syste	
		Consistent and a state of the second second	The Estensi		Manual Manual	Local Suste	
		Emotion Discovery Denvide	The FORMO		Married	Local Sensice	
		C Function Discovery Resourc	Publishes th		Manual	Local Service	
		Google Chrome Elevation 5			Manual	Local Syste	
		Q. Google Update Service (pup	Keeps your _		Automatic (D_	Local Syste	
		Q. Google Update Service (pup	Keeps your		Manual	Local Syste	
		Group Policy Client	The service	Dunning	Automatic (T	Local Syste	
		A Health Key and Certificate	Provides X.5		Manual	Local Syste	

5. Open a browser and start the DocSlide initial setup wizard by visiting: http://localhost:12120

DocSlide	× +		
\leftrightarrow \rightarrow C (i) localhost:1212	20/setup		
Initial setup			
Admin account setup:			
Admin password:			
Repeat admin password:			
Web server configurati	ion		
HTTP 🗸		All local IP addresses 🗸	
Port:		12120	
SSL Certificate			
Authentication type:			
Users will use passwords stored in		Windows 🗸	
Authenticate to link download:		× No, allow anonymous download	
I have read and agree to the EU Full content available here	JLA		
Identifier of this installation: 27444 Licensed to RG VB	029-7636-4b71-9af1-2a6c08511579		
✓ Save			
After setting this up you have to rest	tart service to apply. en 🗸 🗸		

Admin Account Setup

Here you can set the password for the admin account.

Admin account setup:	
Admin password:	
Repeat admin password:	·····

Web Server Configuration

Here you can configure:

• How the portal will be available, either via HTTP or HTTPS.

- The IP address DocSlide will be used if there are more than one.
- The Port number which DocSlide will use.
- The certificate of the server for HTTPS communication (this needs to be created before the installation by an administrator for the DNS name of the server)

Web server configuration								
нттр 🗸)	192.168.66.35	~					
нттр	ĺ							
HTTPS		12120						
SSL Certificate								

Authentication Type

Here you can set, the system against which DocSlide will authenticate users' passwords. In the case of Windows – Integrated Windows Authentication will be used, the options are:

- Windows
- LDAP
- PaperCut

Authentication type:				
Users will use passwords stored in:	Windows	~)	
	Windows			
Authenticate to link download:	Ldap		download	
Identifier of this installation: 88c7a9f6-4a17-4e6f-ab9a-06fb5abaf42c	PaperCut			
Licensed to BC				

Eula confirmation

Here you need to read DocSlide Eula and confirm that you agree with it.



License activation

Copy the server guide and send it via email at EMAIL ADDRESS ITS for license generation. An example guide is shown below:

Identifier of this installation: 88c7a9f6-4a17-4e6f-ab9a-06fb5abaf42c

When you will shortly receive your license file, select it and save it in any folder. After that you need to select it via installation wizard and save it.

	0	Open			×
	🐑 🍥 👻 🕆 📕 🕨 T	his PC + Local Disk (C:) + install +	v ©	Search install	٩
Port:	Organize 👻 New folder	r			
	🔶 Favorites	Name	Date modified	Туре	Size
CCI Contiñente	Desktop	DocSlide	29/07/2020 11:57	File folder	
SSE Certificate	🐌 Downloads	8200862d-8019-4254-9e0b-9f906eaedb93.license	21/07/2020 16:56	LICENSE File	1 K
	Secent places	h DocSlide.zip	29/07/2020 12:24	Compressed (zipp	5,666 K
		dotnet-hosting-3.1.6-win.exe	21/07/2020 16:43	Application	63,296 K
Authentication type:	[툪 This PC				
Users will use passwords stored in: v	두 Network				
Authenticate to link download:					
Identifier of this installation: 88c7a9f6-4a17-4e6f-ab9a-06fb5abaf42c					
+ Select license file					
		۲			>
✓ Save	Filer	ame: 8200862d-8019-4254-9e0b-9f906eaedb93.license	~	All Files (*.*)	~
After setting this up you have to restart service to apply. en				Open Ca	incel

Language Selection

Select your language, e.g. en for English.

en 🗸]
en	
pl	
tr	
	en 🖍 en pl tr

Restart DocSlide Service

After pressing save you need to restart the DocSlide Scanning Service.



Client School Sc	The DNS Cli	Running	Automatic (T	Network S
🔐 DocSlide Scanning Service 👝		Running	Automatic	Local Syste
🔍 Encrypting File System (EFS)	Start		Manual (Trig	Local Syste
Extensible Authentication P.	Stop		Manual	Local Syste
🔍 Function Discovery Provide.	Pause		Manual	Local Service
Resourc	Resume		Manual	Local Service
🔍 Google Chrome Elevation S.	Pertart		Manual	Local Syste
🔍 Google Update Service (gup	Nestan		Automatic (D	Local Syste
🌼 Google Update Service (gup	All Tasks	•	Manual	Local Syste
Group Policy Client	Refresh		Automatic (T	Local Syste
鵒 Health Key and Certificate	D		Manual	Local Syste
	Properties			
omputer	Help			

Logging On to the DocSlide Admin Portal

To login as admin to DocSlide portal open a browser and go to: <u>http://localhost://12120/login/admin</u>

or https://localhost://12120/login/admin depends on what you configure.

← → C (i) localhost:12120/login/admin		
Admin login		
Admin login:	admin	
Admin password:		

You will be logged to the portal as an admin user and you need to switch to the Admin Portal

M				Logout admin 🖌 en 🗸
	Mu Saana			E Logout
Docslide	wy Scans			🛔 Admin Portal
TS DELIVERING INNOVATIVE	List of scans			
✿ My Scans	Refresh	Delete selected		
Send scan to flow	File name	Uploaded	Downloaded	Operations
		н ч 🚺 н		

After that you will see the DocSlide Admin Portal

[©] INFO TECHNOLOGY SUPPLY LTD. 2020

DocSlide	Logout admin. Y en Y			
Home Scanning	Flows: O	Destinations: 0	Working from: 29-07-2020 12:35:11	License: Valid till: 31-12-2020
> Settings > Administration				

Congratulations, good job, DocSlide is installed, and you can start playing with configuration. ③

Backup and Recovery

For backup and recovery, you will need to store the DocSlide database and the *internal.dat* file from the *store* subfolder in a safe place. This will give you the ability to restore the system in under a minute. You can find the DocSlide database as shown below, the folder *store* is available in the root folder of DocSlide:

Name	Date modified	Type
logs	27/07/2020 16:30	File fold
store .	21/07/2020 16:56	File fold
🗼 web	28/07/2020 09:20	File fold
8200862d-8019-4254-9e0b-9f906eaedb93	21/07/2020 16:56	LICENSE
appsettings.Development.json	21/04/2020 20:01	JSON Fi
appsettings.json	12/05/2020 16:05	JSON Fi
Autofac.dll	16/02/2020 14:35	Applica
Autofac.Extensions.DependencyInjection	27/01/2020 22:37	Applica
BouncyCastle.Crypto.dll	10/04/2018 13:45	Applicat
db.litedb	29/07/2020 12:35	LITEDB
db-log.litedb	29/07/2020 12:35	LITEDB I
docslide.service	03/06/2020 16:45	SERVICE

If you have any questions about this release of DocSlide then please do not hesitate to contact ITS Support via email at <u>helpdesk@its-group.com</u> or call +44 (0)20 8869 1960.